

ROS-Nour Face Detection

By:

Belal Rashwan | 201801052
Seif Mohamed | 201801282
Ayatullah Abdelrahman | 201801887



Communications and Information Engineering Department

Supervised by:

Dr. Mostafa El Elshafei

Zewail City of Science, Technology and Innovation,
Giza, 12578, Egypt

June 8th, 2023

The Link of the code folder:

<https://drive.google.com/drive/folders/1dinGb4R1yT7hjfW5pLI2vm-dc8N2t4f0?usp=sharing>

User Manual:

1. First, install Ubuntu 20.04 (Focal Fossa).

2. Open terminal.

3. Install Noetic Ros:

a. Set up your sources.list:

```
sudo sh -c 'echo "deb http://packages.ros.org/ros/ubuntu focal  
main" > /etc/apt/sources.list.d/ros-latest.list'
```

b. Set up the keys:

```
curl -s  
https://raw.githubusercontent.com/ros/rosdistro/master/ros.asc  
| sudo apt-key add -
```

c. Update the package lists:

```
sudo apt update
```

d. Install ROS Noetic Desktop-Full:

```
sudo apt install ros-noetic-desktop-full
```

e. Initialize rosdep:

```
sudo rosdep init  
rosdep update
```

f. Set up the ROS environment variables:

```
echo "source /opt/ros/noetic/setup.bash" >> ~/.bashrc  
source ~/.bashrc
```

g. Install additional dependencies (if needed):

```
sudo apt install python3-rosinstall  
python3-rosinstall-generator python3-wstool build-essential
```

h. That's it! ROS Noetic should now be installed on your Ubuntu 20.04 system. You can verify the installation by running the following command:

```
rosversion -d
```

(follow the installation instructions on wikiros from this [hyperlink](#) for more elaboration).

4. Write the following command:

```
printenv | grep ROS
```

```
source /opt/ros/noetic/setup.bash
```

5. Create a catkin workspace:
 - a. `mkdir -p ~/catkin_ws/src`
 - b. `cd ~/catkin_ws/`
 - c. `Catkin_make`
 - d. `source devel/setup.bash`
6. Download the face recognition code [from this drive link](#).
7. Move the “.deepface” to the “home” directory on your device.
8. Create a catkin package for our code:
 - a. `cd ~/catkin_ws/src`
 - b. `catkin_create_pkg cam_pub std_msgs rospy`
 - c. `cd ~/catkin_ws`
 - d. `catkin_make`
 - e. Source `devel/setup.bash`
 - f. `cd ~/catkin_ws/cam_pub`
 - g. `mkdir scripts`
9. Copy the code you have downloaded in step 6 to the “scripts” folder you just created in `catkin_ws/cam_pub` folder
10. On the same terminal you have opened, write:
 - a. `cd ~/catkin_ws/cam_pub/scripts`
 - b. `Pip install -r requirements.txt`
 - c. `Python3 CamPub.py`